


The background features a complex network diagram with numerous nodes of varying sizes (dark blue, light blue, and grey) connected by thin grey lines. Some nodes are highlighted with larger concentric circles. A dark grey rectangular box is positioned in the lower right, containing the title and subtitle.

DESIGN AGGREGATE STRUCTURE

Supplemental Tool for ePAVE3 Program

OVERVIEW OF SUPERPAVE MIX DESIGN PROCESS

Step 1: Selection of Materials (Binder, Aggregate and Modifiers)

Step 2: Selection of DAS

Step 3: Selection of DAC

Step 4: Moisture Susceptibility Evaluation

Step 5: Rutting Resistance Evaluation

OVERVIEW OF SUPERPAVE MIX DESIGN PROCESS

Step 1: Selection of Materials (Binder, Aggregate and Modifiers)

Step 2: Selection of DAS



Scope of the program

Step 3: Selection of DAC

Step 4: Moisture Susceptibility Evaluation

Step 5: Rutting Resistance Evaluation

SAMPLE GRADATION


NMS: 25.0 mm

Step2: Selection of DAS

Once a group of aggregates has been identified, these aggregates are **combined at different percentages** to produce at least three distinct blends conforming to Superpave gradation requirements according to designed NMS.


4,598,126

POSSIBLE COMBINATION FOR 5 DIFFERENT STOCKPILE



View the Estimated VMA % of Each Blend	Main Menu
Input Values as Needed in the Green Cells	25.0 mm Nominal Maximum Design
Back ...	Next ...

Mix Design Reference No.	0	Page 5 of 13					
Selection of DAS							
Aggregate Gradation							
Sieve Size raised to 0.45 power	Sieve Size		Percentage Passing				
			Samples From the Hot Bins				
	mm	in	Agg. # 1	Agg. # 2	Agg. # 3	Agg. # 4	Agg. # 5
5.81	50.0	2	100.0	100.0	100.0	100.0	100.0
5.11	37.5	1.5	100.0	100.0	100.0	100.0	100.0
4.26	25	1	42.3	100.0	100.0	100.0	100.0
3.76	19.0	3/4	11.9	99.9	100.0	100.0	100.0
3.12	12.5	1/2	1.5	50.3	100.0	100.0	100.0
2.75	9.5	3/8	1.0	12.3	99.5	100.0	100.0
2.02	4.75	No.4	0.6	0.7	22.9	96.6	100.0
1.47	2.36	No 8	0.1	0.2	3.2	62.5	100.0
1.08	1.18	No 16	0.1	0.1	1.3	35.2	100.0
0.79	0.60	No 30	0.0	0.1	0.7	17.0	100.0
0.58	0.30	No 50	0.0	0.0	0.4	7.3	99.7
0.43	0.15	No 100	0.0	0.0	0.2	3.2	93.9
0.31	0.075	No. 200	0.0	0.0	0.1	1.1	77.2
Suggested Blending Percentages							
Blend #	Total	Agg. # 1	Agg. # 2	Agg. # 3	Agg. # 4	Agg. # 5	
Blend 1	0.0						
Blend 2	0.0						
Blend 3	0.0						



USING THE PROGRAM

Demonstration of the program

DESIGN AGGREGATE STRUCTURE

Pick NMS

NMS: 37.5 mm

NMS: 12.5 mm

NMS: 25.0 mm

NMS: 9.5 mm

NMS: 19.0 mm

NMS: 4.75 mm

7F-RA-Mega Thin

8F-RA-Medium Thin

9F-RA-Ultra Thin

EXIT

AASHTO
M323-17(2021)

SUPERPAVE

GRADATION (NMS=25.0 mm)

Back to
Main Menu

Control
Points

in.(mm)	☐ AGG#1	☐ AGG#2	☐ AGG#3	☐ AGG#4	☐ MF or CD
2" (50)	0	0	0	0	0
1-1/2" (37.5)	0	0	0	0	0
1" (25)	0	0	0	0	0
3/4" (19)	0	0	0	0	0
1/2" (12.5)	0	0	0	0	0
3/8" (9.5)	0	0	0	0	0
#4 (4.75)	0	0	0	0	0
#8 (2.36)	0	0	0	0	0
#16 (1.18)	0	0	0	0	0
#30 (0.60)	0	0	0	0	0
#50 (0.30)	0	0	0	0	0
#100 (0.15)	0	0	0	0	0
#200 (0.075)	0	0	0	0	0
VMA %	12				

Enter Gradation

VMA Range
(12-14)

(1) OK

in.(mm)	AGG#1	AGG#2	AGG#3	AGG#4	MF or CD
2" (50)					
1-1/2" (37.5)					
1" (25)					
3/4" (19)					
1/2" (12.5)					
3/8" (9.5)					
#4 (4.75)					
#8 (2.36)					
#16 (1.18)					
#30 (0.60)					
#50 (0.30)					
#100 (0.15)					
#200 (0.075)					

(2) Find Suggested Blends

Suggested Blends with predicted VMA

COARSE BLEND

[Agg1, Agg2, Agg3, Agg4, MF/CD]	VMA(min)=	--
[Agg1, Agg2, Agg3, Agg4, MF/CD]	VMA(max)=	--
[Agg1, Agg2, Agg3, Agg4, MF/CD]	VMA(ave)=	--

FINE BLEND

[Agg1, Agg2, Agg3, Agg4, MF/CD]	VMA(min)=	--
[Agg1, Agg2, Agg3, Agg4, MF/CD]	VMA(max)=	--
[Agg1, Agg2, Agg3, Agg4, MF/CD]	VMA(ave)=	--

COARSE

FINE

in.(mm)	VMA(min)	VMA(max)	VMA(ave)	VMA(min)	VMA(max)	VMA(ave)	Control Points
2" (50)							100
1-1/2" (37.5)							90-100
1" (25)							90
3/4" (19)							
1/2" (12.5)							
3/8" (9.5)							
#4 (4.75)							
#8 (2.36)							19-45
#16 (1.18)							
#30 (0.60)							
#50 (0.30)							
#100 (0.15)							
#200 (0.075)							1-7

(3) View Gradation Curve

SUPERPAVE Design Aggregate Structure (NMS=25.0 mm)

GRADATION (NMS=25.0 mm)

Back to Main Menu

Control Points

in.(mm)	☐ AGG#1	☐ AGG#2	☐ AGG#3	☐ AGG#4	☐ MF or CD
2" (50)	100	100	100	100	100
1-1/2" (37.5)	100	100	100	100	100
1" (25)	42.3	100	100	100	100
3/4" (19)	11.9	99.9	100	100	100
1/2" (12.5)	1.5	50.3	100	100	100
3/8" (9.5)	1	12.3	99.5	100	100
#4 (4.75)	0.6	0.7	22.9	96.6	100
#8 (2.36)	0.1	0.2	3.2	62.5	100
#16 (1.18)	0.1	0.1	1.3	35.2	100
#30 (0.60)	0	0.1	0.7	17	100
#50 (0.30)	0	0	0.4	7.3	99.7
#100 (0.15)	0	0	0.2	3.2	93.9
#200 (0.075)	0	0	0.1	1.1	77.2
VMA %	12				

VMA Range (12-14)

(1) OK

Suggested Blends with predicted VMA

COARSE BLEND

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(min)=

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(max)=

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(ave)=

FINE BLEND

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(min)=

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(max)=

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(ave)=

COARSE

FINE

in.(mm)	VMA(min)	VMA(max)	VMA(ave)	VMA(min)	VMA(max)	VMA(ave)	Control Points
2" (50)							100
1-1/2" (37.5)							90-100
1" (25)							90
3/4" (19)							
1/2" (12.5)							
3/8" (9.5)							
#4 (4.75)							
#8 (2.36)							19-45
#16 (1.18)							
#30 (0.60)							
#50 (0.30)							
#100 (0.15)							
#200 (0.075)							1-7

(2) Find Suggested Blends

(3) View Gradation Curve

GRADATION (NMS=25.0 mm)

Back to
Main Menu

in.(mm)	☐ AGG#1	☐ AGG#2	☐ AGG#3	☐ AGG#4	☐ MF or CD	Control Points
2" (50)	100	100	100	100	100	100
1-1/2" (37.5)	100	100	100	100	100	90-100
1" (25)	42.3	100	100	100	100	90
3/4" (19)	11.9	99.9	100	100	100	
1/2" (12.5)	1.5	50.3	100	100	100	
3/8" (9.5)	1	12.3	99.5	100	100	
#4 (4.75)	0.6	0.7	22.9	96.6	100	
#8 (2.36)	0.1	0.2	3.2	62.5	100	19-45
#16 (1.18)	0.1	0.1	1.3	35.2	100	
#30 (0.60)	0	0.1	0.7	17	100	
#50 (0.30)	0	0	0.4	7.3	99.7	
#100 (0.15)	0	0	0.2	3.2	93.9	
#200 (0.075)	0	0	0.1	1.1	77.2	1-7
VMA %	12					

VMA Range
(12-14)

(1) OK

in.(mm)	AGG#1	AGG#2	AGG#3	AGG#4	MF or CD
2" (50)	100.0	100.0	100.0	100.0	100.0
1-1/2" (37.5)	100.0	100.0	100.0	100.0	100.0
1" (25)	42.3	100.0	100.0	100.0	100.0
3/4" (19)	11.9	99.9	100.0	100.0	100.0
1/2" (12.5)	1.5	50.3	100.0	100.0	100.0
3/8" (9.5)	1.0	12.3	99.5	100.0	100.0
#4 (4.75)	0.6	0.7	22.9	96.6	100.0
#8 (2.36)	0.1	0.2	3.2	62.5	100.0
#16 (1.18)	0.1	0.1	1.3	35.2	100.0
#30 (0.60)	0.0	0.1	0.7	17.0	100.0
#50 (0.30)	0.0	0.0	0.4	7.3	99.7
#100 (0.15)	0.0	0.0	0.2	3.2	93.9
#200 (0.075)	0.00	0.00	0.10	1.10	77.20

(2) Find Suggested Blends

Suggested Blends with predicted VMA

COARSE BLEND

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(min)=

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(max)=

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(ave)=

FINE BLEND

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(min)=

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(max)=

[Agg1, Agg2, Agg3, Agg4, MF/CD]

VMA(ave)=

COARSE

FINE

in.(mm)	VMA(min)	VMA(max)	VMA(ave)	VMA(min)	VMA(max)	VMA(ave)	Control Points
2" (50)							100
1-1/2" (37.5)							90-100
1" (25)							90
3/4" (19)							
1/2" (12.5)							
3/8" (9.5)							
#4 (4.75)							
#8 (2.36)							19-45
#16 (1.18)							
#30 (0.60)							
#50 (0.30)							
#100 (0.15)							
#200 (0.075)							1-7

(3) View Gradation Curve

Check Data Entry
then click Button(2)

GRADATION (NMS=25.0 mm)

Back to
Main Menu

in.(mm)	☐ AGG#1	☐ AGG#2	☐ AGG#3	☐ AGG#4	☐ MF or CD
2" (50)	100	100	100	100	100
1-1/2" (37.5)	100	100	100	100	100
1" (25)	42.3	100	100	100	100
3/4" (19)	11.9	99.9	100	100	100
1/2" (12.5)	1.5	50.3	100	100	100
3/8" (9.5)	1	12.3	99.5	100	100
#4 (4.75)	0.6	0.7	22.9	96.6	100
#8 (2.36)	0.1	0.2	3.2	62.5	100
#16 (1.18)	0.1	0.1	1.3	35.2	100
#30 (0.60)	0	0.1	0.7	17	100
#50 (0.30)	0	0	0.4	7.3	99.7
#100 (0.15)	0	0	0.2	3.2	93.9
#200 (0.075)	0	0	0.1	1.1	77.2
VMA %	12	VMA Range (12-14)		(1) OK	

Control
Points

100

90-100

90

19-45

1-7

Suggested Blends with predicted VMA

COARSE BLEND

14	30	20	30	6	VMA(min)=	12.71
14	15	40	25	6	VMA(max)=	13.97
16	25	30	25	4	VMA(ave)=	13.34

FINE BLEND

14	25	25	30	6	VMA(min)=	12.82
12	25	25	35	3	VMA(max)=	13.76
16	20	30	30	4	VMA(ave)=	13.26

in.(mm)	AGG#1	AGG#2	AGG#3	AGG#4	MF or CD
2" (50)	100.0	100.0	100.0	100.0	100.0
1-1/2" (37.5)	100.0	100.0	100.0	100.0	100.0
1" (25)	42.3	100.0	100.0	100.0	100.0
3/4" (19)	11.9	99.9	100.0	100.0	100.0
1/2" (12.5)	1.5	50.3	100.0	100.0	100.0
3/8" (9.5)	1.0	12.3	99.5	100.0	100.0
#4 (4.75)	0.6	0.7	22.9	96.6	100.0
#8 (2.36)	0.1	0.2	3.2	62.5	100.0
#16 (1.18)	0.1	0.1	1.3	35.2	100.0
#30 (0.60)	0.0	0.1	0.7	17.0	100.0
#50 (0.30)	0.0	0.0	0.4	7.3	99.7
#100 (0.15)	0.0	0.0	0.2	3.2	93.9
#200 (0.075)	0.00	0.00	0.10	1.10	77.20

(2) Find Suggested Blends

COARSE

FINE

in.(mm)	VMA(min)	VMA(max)	VMA(ave)	VMA(min)	VMA(max)	VMA(ave)	Control Points
2" (50)	100.0	100.0	100.0	100.0	100.0	100.0	100
1-1/2" (37.5)	100.0	100.0	100.0	100.0	100.0	100.0	
1" (25)	91.9	91.9	90.8	91.9	93.1	90.8	
3/4" (19)	87.6	87.7	85.9	87.6	89.4	85.9	90
1/2" (12.5)	71.3	78.8	71.8	73.8	75.8	74.3	
3/8" (9.5)	59.7	72.8	62.1	64.1	66.1	66.5	
#4 (4.75)	39.9	39.5	35.3	41.0	42.8	40.1	19-45
#8 (2.36)	25.5	22.9	20.7	25.6	25.7	23.8	
#16 (1.18)	16.9	15.3	13.2	16.9	15.7	15.0	
#30 (0.60)	11.3	10.5	8.5	11.3	9.2	9.3	1-7
#50 (0.30)	8.3	8.0	5.9	8.3	5.6	6.3	
#100 (0.15)	6.6	6.5	4.6	6.6	4.0	4.8	
#200 (0.075)	4.98	4.95	3.39	4.99	2.73	3.45	1-7

(3) View Gradation Curve

GRADATION (NMS=25.0 mm)

Back to
Main Menu

in.(mm)	☐ AGG#1	☐ AGG#2	☐ AGG#3	☐ AGG#4	☐ MF or CD
2" (50)	100	100	100	100	100
1-1/2" (37.5)	100	100	100	100	100
1" (25)	42.3	100	100	100	100
3/4" (19)	11.9	99.9	100	100	100
1/2" (12.5)	1.5	50.3	100	100	100
3/8" (9.5)	1	12.3	99.5	100	100
#4 (4.75)	0.6	0.7	22.9	96.6	100
#8 (2.36)	0.1	0.2	3.2	62.5	100
#16 (1.18)	0.1	0.1	1.3	35.2	100
#30 (0.60)	0	0.1	0.7	17	100
#50 (0.30)	0	0	0.4	7.3	99.7
#100 (0.15)	0	0	0.2	3.2	93.9
#200 (0.075)	0	0	0.1	1.1	77.2
VMA %	12	VMA Range (12-14)		(1) OK	

Control
Points100
90-100
90

19-45

1-7

Suggested Blends with predicted VMA

COARSE BLEND

14	30	20	30	6	VMA(min)=	12.71
14	15	40	25	6	VMA(max)=	13.97
16	25	30	25	4	VMA(ave)=	13.34

FINE BLEND

14	25	25	30	6	VMA(min)=	12.82
12	25	25	35	3	VMA(max)=	13.76
16	20	30	30	4	VMA(ave)=	13.26

in.(mm)	AGG#1	AGG#2	AGG#3	AGG#4	MF or CD
2" (50)	100.0	100.0	100.0	100.0	100.0
1-1/2" (37.5)	100.0	100.0	100.0	100.0	100.0
1" (25)	42.3	100.0	100.0	100.0	100.0
3/4" (19)	11.9	99.9	100.0	100.0	100.0
1/2" (12.5)	1.5	50.3	100.0	100.0	100.0
3/8" (9.5)	1.0	12.3	99.5	100.0	100.0
#4 (4.75)	0.6	0.7	22.9	96.6	100.0
#8 (2.36)	0.1	0.2	3.2	62.5	100.0
#16 (1.18)	0.1	0.1	1.3	35.2	100.0
#30 (0.60)	0.0	0.1	0.7	17.0	100.0
#50 (0.30)	0.0	0.0	0.4	7.3	99.7
#100 (0.15)	0.0	0.0	0.2	3.2	93.9
#200 (0.075)	0.00	0.00	0.10	1.10	77.20

(2) Find Suggested Blends

COARSE

FINE

in.(mm)	VMA(min)	VMA(max)	VMA(ave)	VMA(min)	VMA(max)	VMA(ave)	Control Points
2" (50)	100.0	100.0	100.0	100.0	100.0	100.0	100
1-1/2" (37.5)	100.0	100.0	100.0	100.0	100.0	100.0	
1" (25)	91.9	91.9	90.8	91.9	93.1	90.8	
3/4" (19)	87.6	87.7	85.9	87.6	89.4	85.9	90
1/2" (12.5)	71.3	78.8	71.8	73.8	75.8	74.3	
3/8" (9.5)	59.7	72.8	62.1	64.1	66.1	66.5	
#4 (4.75)	39.9	39.5	35.3	41.0	42.8	40.1	19-45
#8 (2.36)	25.5	22.9	20.7	25.6	25.7	23.8	
#16 (1.18)	16.9	15.3	13.2	16.9	15.7	15.0	
#30 (0.60)	11.3	10.5	8.5	11.3	9.2	9.3	1-7
#50 (0.30)	8.3	8.0	5.9	8.3	5.6	6.3	
#100 (0.15)	6.6	6.5	4.6	6.6	4.0	4.8	
#200 (0.075)	4.98	4.95	3.39	4.99	2.73	3.45	

(3) View Gradation Curve

SUGGESTED COARSE BLEND

COARSE BLEND

14 30 20 30 6


14 15 40 25 6

16 25 30 25 4

VMA(min)= 12.71

VMA(max)= 13.97

VMA(ave)= 13.34



Suggested Blending Percentages

Blend #	Total	Agg. # 1	Agg. # 2	Agg. # 3	Agg. # 4	Agg. # 5
Blend 1	100.0	14.0	30.0	20.0	30.0	6.0
Blend 2	100.0	14.0	15.0	40.0	25.0	6.0
Blend 3	100.0	16.0	25.0	30.0	25.0	4.0

Selection of DAS

Sieve Size raised to 0.45 power	Sieve Size in mm	SUPERPAVE Criteria, % Passing			% Passing			
		Control Points		The Primary Control Sieve	Blend 1	Blend 2	Blend 3	Remarks
		Min	Max					
5.81	50.0			The PCS was introduced in the new AASHTO M323 "Superpave Volumetric Mix Design Specifications", 2005	100.0	100.0	100.0	
5.11	37.5	100.0			100.0	100.0	100.0	
4.26	25.0	90.0	100.0		91.9	91.9	90.8	
3.76	19.0		90.0	It is defined as the sieve size that classifies the gradation between coarse and fine. PCS is specified for each NMS.	87.6	87.7	85.9	
3.12	12.5				71.3	78.8	71.8	
2.75	9.5				59.7	72.8	62.1	
2.02	4.75				39.9	39.5	35.3	
1.47	2.36	19.0	45.0		25.5	22.9	20.7	
1.08	1.18			For 25.0 mm NMS the PCS is 4.75 mm and the % passing at this sieve is 40.0%. If the gradation line passes above the PCS then the gradation is classified as fine otherwise it is classified as coarse.	16.9	15.3	13.2	
0.79	0.60				11.3	10.5	8.5	
0.58	0.30				8.3	8.0	5.9	
0.43	0.15				6.6	6.5	4.6	
0.31	0.075	1.0	7.0		5.0	4.9	3.4	
Based on the PCS Criteria, the gradation of each blend is classified as					Coarse	Coarse	Coarse	

SUGGESTED FINE BLEND

FINE BLEND

14 25 25 30 6


12 25 25 35 3

16 20 30 30 4

VMA(min)= 12.82

VMA(max)= 13.76

VMA(ave)= 13.26



Suggested Blending Percentages

Blend #	Total	Agg. # 1	Agg. # 2	Agg. # 3	Agg. # 4	Agg. # 5
Blend 1	100.0	14.0	25.0	25.0	30.0	6.0
Blend 2	100.0	12.0	25.0	25.0	35.0	3.0
Blend 3	100.0	16.0	20.0	30.0	30.0	4.0


Selection of DAS


Sieve Size raised to 0.45 power	Sieve Size in mm	SUPERPAVE Criteria, % Passing				% Passing			
		Control Points		The Primary Control Sieve		Blend 1	Blend 2	Blend 3	Remarks
		Min	Max						
5.81	50.0			The PCS was introduced in the new AASHTO M323 "Superpave Volumetric Mix Design Specifications", 2005	100.0	100.0	100.0		
5.11	37.5	100.0			100.0	100.0	100.0		
4.26	25.0	90.0	100.0		91.9	93.1	90.8		
3.76	19.0		90.0		87.6	89.4	85.9		
3.12	12.5			It is defined as the sieve size that classifies the gradation between course and fine. PCS is specified for each NMS.	73.8	75.8	74.3		
2.75	9.5				64.1	66.1	66.5		
2.02	4.75				41.0	42.8	40.1		
1.47	2.36	19.0	45.0		25.6	25.7	23.8		
1.08	1.18			For 25.0 mm NMS the PCS is 4.75 mm and the % passing at this sieve is 40.0%. If the gradation line passes above the PCS then the gradation is classified as fine otherwise it is classified as coarse.	16.9	15.7	15.0		
0.79	0.60				11.3	9.2	9.3		
0.58	0.30				8.3	5.6	6.3		
0.43	0.15				6.6	4.0	4.8		
0.31	0.075	1.0	7.0		5.0	2.7	3.4		
Based on the PCS Criteria, the gradation of each blend is classified as					Fine	Fine	Fine		

PURPOSE

This program suggests initial blend of aggregate that conforms to control points or gradation requirements by AASHTO M323 (Superpave).

This program eliminates trial-and-error of different combination and provide distinct blends for the design





BONUS

Thin Layer Design

BONUS



MOT TECHNICAL MANUAL:
FOR THE DEVELOPED
ASPHALT MIXTURES USED
WITHIN THIN LAYERS OF
SURFACE TREATMENT FOR
ROAD MAINTENANCE

Thin Surface Treatment (8F-RA-Medium Thin)

GRADATION (8F-RA-Medium Thin) [Back to Main Menu](#)

Suggested Blends with predicted VMA

in.(mm)	☐ 3/8"	☐ 1/4"	☐ CS	☐ MF/CD
1/2" (12.5)	100	100	100	100
3/8" (9.5)	99.2	100	100	100
1/4" (6.3)	80	100	100	100
#4 (4.75)	13.4	57.6	92.4	100
#8 (2.36)	2.3	14.8	71.2	100
#16 (1.18)	0.4	4.2	47.4	100
#30 (0.60)	0	0.6	27.8	98
#50 (0.30)	0	0	14.6	95
#100 (0.15)	0	0	6.9	81.2
#200 (0.075)	0	0	5.3	70.6
VMA %	17	(17-18) Min VMA= 16.25		

(1) OK

in.(mm)	3/8"	1/4"	CS	MF/CD
1/2" (12.5)	100.0	100.0	100.0	100.0
3/8" (9.5)	99.2	100.0	100.0	100.0
1/4" (6.3)	80.0	100.0	100.0	100.0
#4 (4.75)	13.4	57.6	92.4	100.0
#8 (2.36)	2.3	14.8	71.2	100.0
#16 (1.18)	0.4	4.2	47.4	100.0
#30 (0.60)	0.0	0.6	27.8	98.0
#50 (0.30)	0.0	0.0	14.6	95.0
#100 (0.15)	0.0	0.0	6.9	81.2
#200 (0.075)	0.00	0.00	5.3	70.60

(2) Find Suggested Blends

in.(mm)	VMA(min)	VMA(max)	VMA(ave)	Control Points
1/2" (12.5)	100.0	100.0	100.0	100
3/8" (9.5)	99.9	99.8	99.9	98-100
1/4" (6.3)	97.0	96.0	98.0	
#4 (4.75)	72.3	71.5	69.2	65-85
#8 (2.36)	48.5	49.2	40.4	30-55
#16 (1.18)	32.7	32.0	25.9	20-45
#30 (0.60)	21.0	18.9	16.3	12-30
#50 (0.30)	13.6	10.3	10.6	8-22
#100 (0.15)	8.6	5.2	6.8	5-14
#200 (0.075)	7.10	4.10	5.65	2-10

(3) View Gradation Curve

FINE BLEND

	15	25	54	6
VMA(min)=				
VMA(max)=				
VMA(ave)=				

VMA(min)= 17.00
VMA(max)= 18.94
VMA(ave)= 17.98